## User Manual for the graphomate matrix for Tableau

			Profit	abs
Total			372.8k	-4.1k
Consumer	Total		188.7k	<b>11</b> 1k
	Phones	Total	25.0k	1 <mark>1.8k</mark>
		Central	19.7k	1 .5k
		South	-3.8k	<mark>17</mark> 0k
		North	9.1k	7.4k
	Bookcases	Total	31.1k	20.1k
		Central	7.9k	1.4k
		South	13.9k	11 <mark>.2k</mark>
		North	9.3k	7.4k
	Machines	Total	8.9k	-2.7k
		Central	5.7k	-2.7k
		South	-1.1k	-3.3k
		North	4.3k	3.3k

Version 2020.3 – as of August 2020

https://www.graphomate.com

## graphomate.II

#### **Table of contents**

- Introduction
- Installation
- Quick Start
- graphomate property sheet (GPS)
- Known Issues matrix
- Knwon Issues (Tableau)

### Introduction

The graphomate matrix is our new table component for Power BI, Tableau and SAP Analytics Cloud (SAC).

This allows you to easily realize IBCS-compliant tables, but also to perform various (conditional) formatting, because the graphomate matrix can be designed using its own formatting language - the so-called Cell Formatting Language (CFL). When developing the graphomate matrix, the focus was on performance, horizontal and vertical scrolling, hierarchy displays in rows and columns, and graphical visualization elements:

	Profit	Profit FC	a	bs	perc	
⊿ ACME	372.8k	377.0k	-4.1k		-1%	
	188.7k	199.8k	-11.1k		-6%	
⊿ Corporate	123.4k	🕖 114.9k	i i	8.5k	1 79	6
⊿ Art	8.0k	16.0k	-8.1k		-50%	
Central	5.5k	7.3k	-1.8k		-24%	
South	2.0k	5.0k	-3.1k		-61%	
North	0.5k	3.7k	-3.2k		-87%	
⊿ Paper	2.4k	12.9k	-10.5k		-81%	
Central	1.2k	10.6k	-9.4k		-89%	
North	0.4k	1.2k	-0.8k		-67% -	
South	0.8k	1.1k	-0.3k		-24%	

The graphomate matrix replaces the **graphomate tables**, which we have been offering since 2014. Although the graphomate tables offered the possibility to map IBCS requirements to a table with just a few clicks. However, our customers wanted more formatting options and better performance, especially for large tables. We intend to offer the graphomate matrix not only for the SAP Analytics Cloud (SAC) step by step but also for other SAP Analytics front-ends.

Unfortunately, the SAP Partner Interface (SDK) for SAC currently does not offer the possibility to connect data directly. This is announced for H1.2021. Currently, unfortunately, a script workaround must be worked with to transfer data from a SAC standard visualization element to the graphomate matrix.

In the following we describe the properties of the graphomate matrix as well as the possibility to set them in our user interface. This user interface is almost identical in all BI front ends - Power BI, Tableau and the SAC. Formatting settings of the graphomate matrix can be stored on the graphomate server and used in other environments.

### Installation

#### Adding the graphomate extensions to a Tableau Dashboard

- 1. Save the graphomate.trex file in a folder.
- 2. Open a Dashboard worksheet in a Tableau workbook.
- 3. In a Tableau Dashboard, in the Objects section, select the Extension entry and drag it to the drawing area.
- 4. In the "Choose an Extension" dialog box, do either of the following: Click *My Extensions*, and navigate to a . trex file you previously downloaded.
- 5. If prompted, allow the dashboard extension access to data in the workbook.
- 6. You can now use the extension

To use the graphomate extensions via Tableau Server or Tableau Online, the extensions must be added to the whitelist. Link (Documentation Tableau Online)

After expiration of the trial versions the graphomate extensions in the Tableau Dashboard can not be updated. If you want to continue using the trial dashboards after purchasing the licenses, the extensions have to be loaded into the dashboard, linked to the data and configured again.

## **Quick Start**

#### **First Steps**

- 1. Add a tableau worksheet to your dashboard, which should serve the graphomate component as data basis. graphomate component does not work without this worksheet, because there is no data for visualization otherwise.
- 2. Open the graphomate property sheet by clicking on "Configure..." on the graphomate component.
- 3. The graphomate property sheet should have opened.
- 4. Use the Data Tab to select a tableau worksheet. The data is then transferred to the graphomate component.

5. Use the graphomate property sheet to influence the configuration of the graphomate component. tableau.mp4

## graphomate property sheet (GPS)

- Data Tab
- Labels Tab
- Axes Tab
- Chart Specific Tab
- Input Output Tab
- Default values

The following usage structure can be found in all graphomate extensions with the graphomate property sheet (GPS):

SEARCH FIELD	graphomate 💵 bubbles 🔍 💸 🚺
Use the search field to quickly find a setting (example "Title") and change it.	🗎 TT 💽 🗽 🗊 🖉 🗐
CONNECTION TO THE GRAPHOMATE SERVER	Input Output
active connection to graphomate server	Server ^
no active connection to the graphomate server	https://
INFO TAB	
In the header of the GPS there is an info symbol ( $[$ ). Cli	Info
ck on the 🛄 icon to open a tab with relevant information:	Version: 2020.3.0
<ul> <li>the version number of the installed extension (important information for the support)</li> </ul>	Documentation
<ul><li>link to the graphomate Support Desk</li><li>to the general terms and conditions</li></ul>	Please use <u>this link</u> to submit errors or ideas for improvement.
<ul><li>to the graphomate website and</li><li>a list of the software libraries used (Credits)</li></ul>	The General Terms of Licence and Maintaining of the graphomate GmbH apply.
	© 2020 graphomate GmbH, D-Kiel, <u>www.graphomate.com</u>
	Credits ~
	CLOSE

1

4

CHECKBOXEN An active property is indicated by a white check mark in the checkbox. To deactivate it, click on the checkbox again.	Additional Information       ^         ☑ Legend       _         □ Tooltip       _
COLOR PICKER You can enter the color value as HEX code or click on the colored circle. Use the Color Picker or enter color values as HEX, RGB, or HSL code. You switch between these color models using the small arrows on the right side of the color picker.	Deviations       ^         Good Color       #8CB400         Bad Color       #FF0000         Invert       Invert
	Good Color
ADDING NEW ELEMENTS TO LISTS Click on the	Scenario Definition

OK

Measures

Dimension

Measures

Members

budget

#### FILTER OPTION

In some cases, it is necessary that several settings are only applied to certain key figures, dimensions or dimensional characteristics. You can use the filter option to define the combination to which the setting is to be applied.

In the example on the left, the desired setting is only applied to the key figure "budget". This can be, for example, a certain number formatting, a scenario or a certain icon for displaying the key figure.

Filter states can be defined in the following settings of graphomate extensions:

- graphomate matrix
  - Value Format
  - Calculations/Deviations
  - Scenario Assignment
  - Bar Chart Assignment
  - Pin Chart Assignment
  - Background Bar Assignment
- graphomate bubbles
  - Value Format
- graphomate pictograms
  - Pictograms/Icon Assignment

#### Input mode: Field / comma separated list (csv)

Properties with the symbol allow the definition of settings on the graphomate property sheet in two

variants. The mode can be changed by clicking on the symbol. The following modes are available:

- 1. per field: The value is entered per field. After one field has been filled, another field is created automatically.
- 2. As a list: The entry is made as a comma-separated list.

Example: Application of the scenarios to elements of a series (see picture)

The first series contains two forecast values (FC) and two budget values (BU). The second series contains only values from the previous period (PP). You can enter the assignment of the scenarios as follows:

Variant per field for series 1: FC (field 1), FC (field 2), BU (field 3), BU (field 4)

Variant as list for series 2: PP,PP,PP,

Scenario Assignment	
Scenarios 1 csv	
FC FC BU BU	
Scenarios 2 🔤 PP,PP,PP,PP,	
Scenarios 3	
Scenarios by Series +	
no items	
Scenarios In Axis	
Scenario Legend Enabled	
Scenarios In Deviations	
	_

+

#### Data Tab

#### CALCULATION

#### Deviations

This property can be used to calculate deviations. It is a list, where each individual element represents the calculation of a new deviation member. The variances are calculated as follows:

#### Absolute: Minuend - Subtrahend Percentage: (Minuend - Subtrahend) / |Subtrahend|

Please note: At this point only the values for deviations are calculated. You have the possibility to visualize these calculated values on the tab "Chart Specific".

#### **Deviations Pop-Up**

You can create new variances using the <sup>th</sup> sign. Each configuration has the following properties:

- *New Member Key:* The unique name of the newly calculated member that is displayed in the table.
- *Type: either Absolute* or *Percent*. Defines whether an absolute or relative deviation is calculated.
- *Target Dimension*: The dimension in which the new, calculated deviation member should be inserted e.g. "measures".
- *Minuend Member*. The member that is to serve as a minuend, e.g. an actual value.
- Subtrahend Member. The member that is to serve as subtrahend, e.g. a value from the previous year.
- *Filter* (optional): A list of filter objects. Each filter object can restrict a dimension to certain members. Only deviation data points are created that correspond to the filter conditions.
- Description: Short name that describes the configuration to be recognizable e.g. "abs"

#### Sort Configurations

Here you can sort members of dimensions. Measures are also interpreted as a dimension and can be sorted accordingly.

In future versions we will extend these options.

#### Sort Configurations Pop-up

# graphomate.II matrix Q

Data

#### Calculations

Deviations

no items

Sort Configurations

no items

Aggregation Type

NULL SUM MIN MAX COUNT

Aggregation Node Name Overall

## Deviation

New Member Name

Type
Absolute
Target Dimension
Target Dimension
Minuend Member
Subtrahend Member
Filter (optional)
Description (optional)

You can use the <sup>th</sup> sign to create new sort orders for dimensions. Each configuration has the following properties:

- *Dimension:* A dimension the members of which should be sorted.
- *Member:* Here you can use drag and drop to sort the members of a dimension or measures.
- *Description:* Short name describing the configuration to be recognizable

#### Aggregation Type

The graphomate matrix calculates aggregations for displaying hierarchy nodes, if the host environment doesn't provide them.

Here you can select the type of aggregation - the default setting is "Sum".

#### Aggregation Node Name

At this point, a separate name can be assigned to the aggregation elements - e.g. "Sum" or Total" or also "Europe".

## Sort Configuration 1

Dimension

Measures 
Members

gross

budget

imdb\_rating

runtime

certificate

sex \_and\_nudity

violence\_and\_gore

profanity

alcohol\_and\_drugs

oscar\_nominations

profanity small

Description (optional)

#### SCENARIO DEFINITION

This property determines the appearance of the scenarios - previously known as Data Types.

The four standard scenarios of the International Business Communication Standards are already defined, but can also be adapted.

You can create new variants using the <sup>th</sup> sign.

#### Scenario Definition Pop-Up

Each scenario has the following characteristics:

- Identifier: A character string (such as AC) that can be used to reference the scenario - for example, in the Scenario Assignment below.
- *Color*: Here you can define the color using the color picker or enter a HEX, RGB or HSL code. You can switch these using the small arrows on the right side of the color picker.
- *Fill Type*: You can choose from the following fill patterns: *Filled*, without filling (*Empty*), hatching down (*Hatched Down*), hatching thick down (*Hatched Down Bold*), hatching up (Hatched Up), hatching thick up (*Hat ched Up Bold*), and dotted (*Dotted*).
- Shape: Refers to the pinheads. The following shapes are available: circle (circle), rectangle (rect), rhomb (rho mb), wedge (wedge), no symbol (none).
- *Width*: This property is not used in the graphomate matrix.
- Font Weight: Choose between normal or bold font size for this scenario.

#### Import/Export

Copy this string to use scenarios in other graphomate components.

	+
AC	
PP	
BU	
mport / Export	
V3sic2hvcnQiOiJBQyIsIr	

Identifier		
AC		
Color	000	
#222	222	
Fill Type		
Filled		*
Shape		
🔲 rect		-
Width		
40		
percent	absolute	
Font Weig	ht	
normal		Ŧ

SCENARIO ASSIGNMENT		
	Scenario Assignment	^
Scenarios in Column Headers	Scenarios in Column Headers	
This property ensures that the scenarios are displayed as		+
bars below the column headers.	no items	
You can use the $^\pm$ sign to create assignments of		
scenarios to dimension members. These can also be used for bar, pin, and background bars		
and their axes - see the tab "Chart Specific".	AC	
Scenario Assignment Pop-Up		
	Scenario Id	
This property assigns scenarios to data cells.	AC	
Each configuration has the following properties:	Filter (optional)	+
• Scenario Id: The ID of the scenario to be used. A	no items	
scenario ID used here, has to be defined in the scenario definition.	Description (optional)	
• Filter. The selected scenario is assigned for each		
dimension member that is selected here using the $^\pm$		OK
sign.		OK
<ul> <li>Description: Short name describing the configuration to be recognizable.</li> </ul>		

#### Labels Tab

#### TITLE graphomate . I matrix Q Title Text Тτ th, Enter the title for the matrix in this field. Multiple-line texts Labels are reproduced accordingly, i.e. the line break is adopted. Title Size Enable Enter the size of the title's font. Select a CSS unit from the Title Text list (such as px, em), Size 14 рх FONT Font Size Size 12 рх Enter the size of the font. Select a CSS unit from the list (such as px, em), Family Arial Family Color Define the global font. You can choose between Arial, #000000 Tahoma, Lucida Console, Verdana and Calibri or type in the name of a font which is installed on your system. Text Ellipsis Color This property defines the font color as HEX, RGB or HSL code. You can open a color picker by clicking on the colored circle and switch the color model by using the small arrows on the right. Alternatively, you can also use the color picker. Text Ellipsis When this option is selected, long character strings are not wrapped but abbreviated with three dots - e.g. electronic prod...

#### VALUE FORMAT

With the Value Format you define the way the values are displayed in the matrix. You can define several formats and assign them to specific columns using filtering. Multiple Value Format Rules (Assignments) are prioritized in descending order, i.e. definitions that are lower in the list overwrite those above them when there filters overlap. Therefore, the generally valid format of the table should be defined at the top of this list without any further filters. Value Formats defined below, restricted by filters, overwrite the formatting defined above - "From General to Special".

#### Value Format Assignment

You can access the configuration by clicking on an element in the list. You define another Value Format by clicking on the  $\oplus$  symbol.

#### Value Format Pop-Up

Define the number format using the following options:

- *Locale:* Defines abbreviations, decimal and thousand separators for the respective language. You can choose between *en*, *de*, *fr* and *auto*. If *auto* is selected, the Locale set in the respective host application is used.
- *Format Type:* Defines the type of number output. You can choose between *number* (decimal number), *percent* (percentage) and *ordinal* (ordinal number).
- Abbreviations: Defines the type of abbreviations. You can choose between *mean* (abbreviation most suitable for the mean value), *min* (abbreviation most suitable for the minimum value), *max* (abbreviation most suitable for the maximum value), *auto* (best-suited abbreviation for each respective number individually), *tr illion* (trillion abbreviation), *billion* (billion abbreviation), *million*, *thousand* and *none* (no abbreviation at all). With this property you can, for example, ensure that numerical values are always displayed in thousands e.g. 0.1k or 1000k.
- *Negative Sign:* Defines how negative numbers are displayed. You can choose between *minus*, *parenthesis*, and *none* (no sign).
- Prefix: The input value is placed before the number.
- *Suffix:* The input value is placed after the number.
- *Thousands Separator:* Replaces the thousand separator set by the selected *locale.*
- Decimal Separator: Replaces the decimal separator set by the selected *locale*.
- Total Digits: Defines how many digits the number may consist of. Total Digits is prioritized over Decimal Digits.

#### Value Format

Value Format Assignment

en-US number

Text Align

left center right

- *Decimal Digits:* Defines how many decimal places of the formatted number are displayed.
- Scaling Factor: The value of each data point is multiplied by the entered number to scale values.
- *Zero Format:* When the checkbox is activated, any data value equal to 0 (the number zero) gets replaced by the entered value.
- *Null Format:* Any data value that equals *NULL* (no value) gets replaced by the entered value.
- *Error Format:* If a data value is undefined or the result of an arithmetic error such as dividing by 0 (zero), the data value is replaced by the entered value.
- Rounding Method: Defines the rounding method. You can choose between half up (23.5 24, -23.5 -23), com mercial (23.5 24, -23.5 -24) and trim (23.5 23, -23.5 23).
- *Explicit Positive Sign:* Defines whether a positive number should always be preceded by a + (plus sign).
- Filter (optional): By clicking in the empty list or on the

 symbol, you can define one or more dimension members for which these format settings should apply.
 For example, you select a measure column using the dimension "measures" and the actual measure (e.g. "gross") of the column to be formatted.

• *Description:* Short name that describes the configuration to be recognizable

#### Text Alignment

Specify how text content is aligned in the matrix: leftaligned (left), centered (center) and right-aligned (right).

## en-US number

Localo

Lucale
en-US 🔹
Format Type
number 🔹
Abbreviations
auto 👻
Negative Sign
minus -
Prefix
I TOUX
Suffix
Sullix
These and One contex
Thousand Separator
Decimal Separator
Total Digits (approx.)
Decimal Digits
1
Scaling Factor
1
Zero Format
Null Format
Null Format
Infinity Format
minity Format
Rounding Method
commercial 🔹
Explicit Positive Sign
Filter (optional)
no items
Description (optional)

leasures	Measures
	Dimension Measures
	Members
ross 👻	gross
ок	

+

#### SCRIPTED FORMATTING

#### CFL Rules

Learning from the usage of our first table component - the graphomate tables - we decided to offer our customers a possibility to format the graphomate matrix very individually according to their ideas. The Cell Formatting Language (CFL) let you define rules which are executed for each cell of the matrix. These rules can be used to influence the display of cells based on cell properties, data properties or matrix properties. In this way, you can create a heat map, color elements, or apply conditional formatting from the graphomate matrix with a few lines of code.

Cell Formatting Language:

The CFL is a script language for individual formatting of the graphomate matrix based on JavaScript syntax.

It allows to read from and write various properties to the global variable *cell* via *getter* and *setter*. A complete API documentation can be found here.

To simplify the programming of the CFL, we provide a web-based CFL editor from which the defined rules can be easily copied and pasted into the script body. This editor and some code templates can be found here.

For all CSS properties and values that can be set in the CFL, the usual notations apply.

#### CFL-Pop-Up

The following properties can be defined:

- *Enabled:* This Boolean property makes it possible to (de)activate the rule.
- Name: A name that is used to identify the rule.
- *Script Body*: This String property contains the actual script in the CFL (Cell Formatting Language)

Scripted	Formatting

CFL Rules

#### no items

## my cfl rule



Name

my cfl rule

Script Body

#### HIERARCHY NODES

Here you control the color and font style of the hierarchy nodes in the table.

#### Color

Here you define the font color of the Hierarchy Nodes. The color overwrites the general font Color from the Font group. Use the Color Picker or enter color values as HEX, RGB, or HSL code. You switch between these color models using the small arrows on the right side of the color picker.

#### Bold

If you want hierarchy nodes to be displayed in bold, activate this property.

#### Italic

If hierarchy nodes should be displayed in italics, activate this property.

#### Indentation

Specify the size of the indentation of hierarchy nodes here. The indentation that is ultimately used is a multiple of the indentation set here and depends on the hierarchy level of the respective node. Select a CSS unit from the list (such as px, em).

#### Node Divider Thickness

Set the thickness of the horizontal separator lines below cells whose rows represent hierarchy nodes. All other separators can be set in the tab *Axes*.

#### Node Divider Color

Here you can set the color of the horizontal separator lines below cells whose rows represent hierarchy nodes. All other separators can be set in the tab *Axes*.

#### Node Divider

Here you can switch the visibility of horizontal separators below cells whose lines represent hierarchy nodes on or off. All other separators can be set in the tab *Axes*.

#### Collapsible

If the hierarchy should be expandable and collapsible, activate the *Collapsible* property.

Hierarchy N	lodes	
Color		
#00000	0	
🖌 Bold		
🔲 Italic		
Indentation		
1,2	em	
Node Divider	Thickness	
0,1	em	Ŧ
Node Divider		
🔽 Node Div	ider	
🔽 Collapsib	le	

STYLING         Matrix Background Color         Determine the background color of the matrix using Color         Picker or HEX, RGB or HSL code. You can switch this         using the small arrows on the right side of the color picker.         Matrix Padding         This property determines the outer padding of the matrix component. Select a CSS unit (such as px, em) from the list.	Styling         Matrix Background Color         #FFFFF         Matrix Padding         10       px	^
FOOTER Footer Text Enter the Footer text for the matrix in this field. Multiple- line texts are reproduced accordingly, i.e. the line break is adopted. Size Enter the footer's font size. Select a CSS unit from the list (such as px, em),	Footer         Enable         Footer Text         Size         12       px	^

#### Axes Tab

#### COLUMNS

#### Default Width [px]

At this point, define the default value for column width in px.

#### Width Per Column [px]

This property allows you to set an individual width for each column of the matrix. The specification is made as a list. The indices of the list correspond to the column indices in the table. The column at position 0 corresponds to the row titles. The width is specified in pixels. For a table with one row title column, two data columns and one calculation column, a sample list would look like this: [200, 0, 0, 300].

If the value 0 is set for one or more columns, the value of the property Default Width is used for these columns.

With the csv-button you have the possibility to enter the column widths as a list of comma separated values.

#### **Column Margins**

This property sets the distance between columns, in any CSS length unit.

#### Supress Repeating Header

If members repeat themselves consecutivley in a column header row, this property can be used to display them only once in succession.

#### Header Dividers

Here you can set the visibility of the horizontal separator lines below column header cells.

#### Header Divider Thickness

Here you can set the thickness of the horizontal dividing lines of column header cells. Select a CSS unit from the list (such as px, em).

#### Header Divider Color

Here you set the color of the horizontal separator lines of column header cells as HEX, RGB or HSL code. You can switch this using the small arrows on the right side of the color picker, which can be opened by clicking on the colored circle.

aphomate	.II matrix Q		î ?
	Тт 🔭	(0)	ŧ
Axes			
Columns	5		^
Default Wi	dth [p×]		
120			
Width Per	Column [px] csv		
200			
Column M	argins		
0,3	em	*	
Suppr	ess Repeating I	leader	
		100001	
_	er Dividers		
	ider Thickness		
0,1	em	*	
Header Di	/ider Color		
#000	000		

#### ROWS

#### Supress Repeating Row Header

If members repeat themselves consecutivley in a row header column, this property can be used to display them only once in succession.

#### Dividers

Here you set the visibility of the horizontal separator lines below data cells and row header cells whose rows are leaves of a hierarchy. That includes all rows which are neither column headers nor hierarchy nodes.

#### **Divider Thickness**

Set the thickness of the horizontal separator lines below cells whose rows are leaves in a hierarchy. That includes all rows which are neither column headers nor hierarchy nodes. Select a CSS unit from the list (such as px, em),

#### **Divider Color**

Here you set the color of the horizontal separator lines below cells whose rows are leaves in a hierarchy. That includes all rows which are neither column headers nor hierarchy nodes. Set the color as HEX, RGB or HSL code. You switch this using the small arrows on the right side of the color picker which can be opened by clicking on the colored circle.

#### Initial Expand Level

Here you can set the starting drilldown state of the row hierarchy. "0" only shows the root node.

#### Alternate Row Styling

This property makes the rows of the matrix alternately white and light gray which makes it easier to perceive individual rows.

#### Crosstab-like Row Headers

Activate this property to split up the row header's hierarchy levels into separate columns.

Rows		^
Suppress Repeating Row Header		
<ul> <li>Dividers</li> </ul>		
Divider Thickr	less	
0,05	em 💌	
Divider Color	03	
Initial Expand	Level	
🔲 Alternate	Row Styling	
🔲 Crosstab	-like Row Headers	

#### **Chart Specific Tab**

#### CHARTS

In this tab you configure visual elements like bar or pin charts in the graphomate matrix.

#### Bar Chart Assignment

This property determines which data should be displayed as an In-Cell Bar Chart type instead of a number. This can be both source data and calculated measures - tab *Data*: *C alculations.* This is a list, whereby each individual list element represents an independent configuration.

Click on the  $\pm$  sign or in the empty list to make settings for the bar charts.

#### Bar Chart Assignment Pop-Up

graphomate . Il matrix Q	î
🗧 Tr 🗽 🔟	ŧ
Chart Specific	
Charts	^
Bar Chart Assignment	+
no items	
Pin Chart Assignments	+
no items	
Good Color #8cb400	
Bad Color	
e #ff0000	
Outlier Style	

- Labels: determines whether the value of the cell should be displayed as a label next to the chart's bar.
- Scenario Id for Axis: Sets a defined scenario for the axis.
- Scenario Id for Bar. Sets a defined scenario for the bar. Scenarios are defined on the first tab Data.
- Negative Value is Good: To swap the meaning of negative and positive colors, activate this property.
- Comparison Group ID: All In-Cell-Bar Charts of a graphomate matrix with an identical Comparison Group ID any string are scaled in the same way. In a later release this will also be possible across multiple graphomate matrix instances.
- Use Outlier Threshold: Specify here whether the Outlier Thresholds should be applied to the scaling.
- Positive Outlier Threshold: Describes the upper limit value of the scaling. All values that are greater than this limit value are displayed as outliers and are not included in the scaling. The next lower value of the scale or total scale (if a Comparison Group is used) then determines the new maximum of the scaling.
- Negative Outlier Threshold: Describes the lower limit value of the scaling. All values that are smaller than this limit value are displayed as outliers and are not included in the scaling. The next larger value of the scale or total scale (if a Comparison Group is used) then determines the new minimum of the scaling.
- Filter(optional, Pop-Up): By clicking in the empty list or on the <sup>+</sup> symbol, you can define one or more dimension members for which the bar charts should be displayed. You could, for example, select the dimension "measures" and the member "Revenue" to display bar charts in all columns representing the
- Description: Short name that describes the configuration to be recognizable.

#### Pin Chart Assignment

measure "Revenue".

This property determines which data should be displayed as an In-Cell Pin Chart type instead of a number. This can be both source data and calculated measures - tab *Data*: *C alculations.* This is a list, whereby each individual list element represents an independent configuration.

Click on the <sup>th</sup> sign or in the empty list to make settings for the pin charts.

#### Pin Chart Assignment Pop-Up

## Bar Chart Assignment

🗸 Labels

Scenario Id for Axis

Scenario Id for Bar

Negative Value is Good

Comparison Group Id

Use Outlier Threshold

Positive Outlier Threshold

100

Negative Outlier Threshold -100

Filter (optional)

no items

Description (optional)

- Labels: determines whether the value of the cell should be displayed as a label next to the chart's pin.
- Scenario Id for Axis: Sets a defined scenario for the axis.
- Scenario Id for Pin: Sets a defined scenario for the pin. Scenarios are defined on the first tab Data.
- Negative Value is Good: To swap the meaning of negative and positive colors, activate this property.
- Comparison Group ID: All In-Cell-Pin Charts of a graphomate matrix with an identical Comparison Group ID any string are scaled in the same way. In a later release this will also be possible across multiple graphomate matrix instances.
- Use Outlier Threshold: Specify here whether the Outlier Thresholds should be applied to the scaling.
- Positive Outlier Threshold: Describes the upper limit value of the scaling. All values that are greater than this limit value are displayed as outliers and are not included in the scaling. The next lower value of the scale or total scale (if a Comparison Group is used) then determines the new maximum of the scaling.
- Negative Outlier Threshold: Describes the lower limit value of the scaling. All values that are smaller than this limit value are displayed as outliers and are not included in the scaling. The next larger value of the scale or total scale (if a Comparison Group is used) then determines the new minimum of the scaling.
- *Filter(optional, Pop-Up):* By clicking in the empty list or
- on the <sup>th</sup> symbol, you can define one or more dimension members for which the pin charts should be displayed. You could, for example, select the dimension "measures" and the member "Revenue" to display pin charts in all columns representing the measure "Revenue".
- Description: Short name that describes the configuration to be recognizable.

#### Good Color

Here you can set the color for positive connoted values by clicking on the corresponding colored circle to open the color picker.

#### Bad Color

Here you can set the colors for negatively connoted values by clicking on the corresponding colored circle to open the color picker.

#### **Outlier Style**

## Pin Chart Assignments

🔽 Labels

Scenario Id for Axis

Scenario Id for Pin

Comparison Group Id

Use Outlier Threshold

Positive Outlier Threshold

100

Negative Outlier Threshold

-100

Filter (optional)

no items

Description (optional)

Here you can select how outliers are displayed. In *SHORT* mode, the outliers are displayed as small triangles on the axis. In *LONG* mode, however, the outliers are displayed over the entire available area according to IBCS rules.

#### BACKGROUND BARS

#### Background Bar Assignment

This property determines which data should be displayed as an In Cell Background Bar instead of a number. This is a list, whereby each individual list element represents an independent configuration.

#### Background Bar Assignment Pop-Up

- Scenario Id: Sets the defined scenario for the background bar. Scenarios are defined on the first tab Data.
- *Negative Value is Good*: To swap the meaning of negative and positive colors, activate this property.
- Comparison Group ID: All background bars of a graphomate matrix with an identical Comparison Group ID - any string - are scaled the same way. In a later release this will be possible across multiple graphomate matrix instances.
- Use Outlier Threshold: Specify here whether the Outlier Thresholds should be applied to the scaling.
- Positive Outlier Threshold: Describes the upper limit value of the scaling. All values that are greater than this limit value are displayed as outliers and are not included in the scaling. The next lower value of the scale or total scale (if a Comparison Group is used) then determines the new maximum of the scaling.
- Negative Outlier Threshold: Describes the lower limit value of the scaling. All values that are smaller than this limit value are displayed as outliers and are not included in the scaling. The next larger value of the scale or total scale (if a Comparison Group is used) then determines the new minimum of the scaling.
- Filter(optional, Pop-Up): By clicking in the empty list or

on the <sup>+</sup> symbol, you can define one or more dimension members for which the background bars should be displayed. You could, for example, select the dimension "measures" and the member "Revenue" to display pin charts in all columns representing the measure "Revenue".

• Description: Short name that describes the configuration to be recognizable.

#### Background Bar Good Color

# Background Bars Background Bar Assignment no items

Background Bar Good Color

#4dacc6

Background Bar Bad Color #c6674d

Background Bar Negative Right to Left

## Background Bar Assignment

Scenario Id

Negative Value is Good
 Comparison Group Id

Use Outlier Threshold

Positive Outlier Threshold 100

Negative Outlier Threshold -100

Filter (optional)

no items

Description (optional)

Here you can set the color for positive connoted values of background bar cells by clicking on the corresponding colored circle to open the color picker.

#### Background Bar Bad Color

Here you can set the color for negative connoted values of background bar cells by clicking on the corresponding colored circle to open the color picker.

#### Background Bar Negative Right To Left

If this property is active, background bars representing a negative value start at the right edge of the cell.

#### Input Output Tab

The functions of this tab are used to exchange templates for the graphomate matrix. Connect to the graphomate server - a free component of graphomate GmbH - to store or load a graphomate matrix template. This way you can exchange preconfigured graphomate matrix designs between BI frontends that support the graphomate server. Currently these are: Power BI, Tableau, Excel, Lumira Designer, Web Intelligence, SAP UI5, SAC.

#### SERVER 2 graphomate II matrix Q Here you enter the URL of the graphomate server to which Τт 11. the component should connect and from which you want to save or retrieve templates. Input Output If you have entered the URL to the server, a green check mark indicates that a connection could be established. Server If another server is used later, the button next to the save URL button can be pressed and the server URL can be edited. https:// The hyperlink "Admin" allows you to jump to the admin Save] area of the graphomate server. TEMPLATES Templates If the current settings are to be saved as a template, a Create Template new template name can be entered in the input field Name labeled Create Template and confirmed by clicking the Sav Save State e State button. If the entered name complies with the naming convention, the template is saved on the server Choose Template and a toast with the corresponding message is displayed in the lower part of the graphomate property sheet. However, if the entered name does not meet the expected Apply][1][C naming conventions, an error message with the permitted characters is displayed accordingly. With Choose Template templates stored on the server can be retrieved and applied. To do this, the desired template must only be selected and the Apply button must be pressed. If you want to delete a template, you have to select the template in the list and press the Delete (bin symbol) button. If changes have been made to the templates on the server side, you have to click on the Refr esh button. Changes should then be visible.

#### **Default values**

Here you will find the default values of the preset Scenarios. Copy the character string and paste it back into the Data tab in the relevant Import/Export area.

#### Scenarios (AC, FC, PP, BU):

W3sic2hvcnQiOiJBQyIsImNvbG9yIjoiIzIyMjIyMiIsImZpbGx0eXBIIjoiZmIsbGVkIiwic2hhcGUiOiJyZWN0liwid GhpY2tuZXNzIjoxLCJiYXJ3aWR0aCl6MC40LCJwaW53aWR0aCl6MC4yNSwiZm9udHdlaWdodCl6Im5vcm 1hbCJ9LHsic2hvcnQiOiJQUCIsImNvbG9yIjoiIzgwODA4MCIsImZpbGx0eXBIIjoiZmIsbGVkIiwic2hhcGUiOiJ yaG9tYiIsInRoaWNrbmVzcyI6MSwiYmFyd2lkdGgiOjAuNCwicGlud2lkdGgiOjAuMjUsImZvbnR3ZWInaHQiOi Jub3JtYWwifSx7InNob3J0IjoiQIUiLCJjb2xvciI6liMwMDAwMDAiLCJmaWxsdHIwZSI6ImVtcHR5Iiwic2hhcGU iOiJjaXJjbGUiLCJ0aGlja25Ic3MiOjEsImJhcndpZHRoljowLjQsInBpbndpZHRoljowLjI1LCJmb250d2VpZ2h0Ij oibm9ybWFsIn0seyJzaG9ydCI6lkZDIiwiY29sb3liOiIjMDAwMDAwIiwiZmIsbHR5cGUiOiJoYXRjaGVkVXAiL CJzaGFwZSI6InJob21iIiwidGhpY2tuZXNzIjoxLCJiYXJ3aWR0aCl6MC40LCJwaW53aWR0aCl6MC4yNSwi Zm9udHdlaWdodCl6Im5vcm1hbCJ9XQ==

## Known Issues matrix

• The performance of the virtual scrolling technology is negatively influenced by browser extensions that react to changes in the HTML structure. We have noticed this, for example, with ad blockers or some extensions to enlarge thumbnails.

## Knwon Issues (Tableau)

- The Comparison Group is only supported in the Tableau Online version.
- Not supported
  - PDF Export
    - own CSS Classes
  - global scenarios, (These must be created per graphomate visual and can be made available via the graphomate server or the import/export string)
  - Scripting